

CAT® VISIONLINK® RELEASE NOTES

January 2021

VisionLink

NEXT GENERATION ASSET MONITORING & FLEET MANAGEMENT

VisionLink Offers:

- Customizable dashboards
- Dynamic reporting capabilities
- Actionable information to make key decisions to help you improve your bottom line
- Navigate easily through the intuitive and mobile-ready interface
- Available in multiple languages

WHAT'S NEW

- VisionLink Unified Fleet
 - First Engine Start and Last Engine Stop events are now displayed in Utilization Details
- VisionLink Unified Service
 - Maintenance tracking can be enabled or disabled for any asset using the new Asset Tracking feature.
 - VisionLink now tracks maintenance only for assets that have had maintenance activities recorded within the last 24 months.
 - If you track maintenance activities for more than 2000 assets, now you specify a working set of fewer than 2000 assets using filters.

NEW FEATURES AND ENHANCEMENTS

Unified Fleet

Two new optional columns can now be displayed in the **Utilization Details** page and report:

- **First Engine Start**
- **Last Engine Stop**

When you make these columns visible in **Settings**, these events are shown in the **Utilization Details** page and report. This information is helpful for understanding when the asset is operating every day compared to estimated runtime targets.


Reported Time	First Engine Start Time	Last Engine Stop Time
01/19/21 23:36 IST	01/19/21 14:31 IST	01/19/21 21:21 IST
01/18/21	-	-
01/15/21 12:00 IST	01/15/21 07:12 IST	01/15/21 12:00 IST

If an asset was first started on a previous day or last stopped on the next day, then a dash (-) is shown for First Engine Start and Last Engine Stop on the single day.

Unified Service

You can now choose to enable or disable maintenance tracking for any asset in the **Maintenance Asset Details** page using the new **Asset Tracking** feature. This feature is ideal for configuring which services you want to track, and when you want to track the services, for each asset as needed.

1. In Unified Service **Maintenance Summary**, select the asset whose maintenance tracking you want to disable.
2. Select **Actions bar / Asset Tracking**.



3. Select **Disable** and select **Apply**. You will see a confirmation message telling you disabling the asset's maintenance tracking will remove it from the **Maintenance** screens until you enable it.
4. Select **Apply**.

In addition, VisionLink now tracks maintenance only for assets that have had maintenance activities recorded within the last 24 months. Maintenance tracking for assets whose last maintenance activity was recorded more than 24 months ago is automatically disabled in VisionLink. Even if an asset's maintenance tracking is disabled, its maintenance history is still visible in VisionLink. Disabled maintenance tracking can be enabled at any time.

In **Maintenance**, if you track maintenance activities for more than 2000 assets, now you specify a working set of fewer than 2000 assets using filters. This feature improves VisionLink performance while enabling you to concentrate on selected assets.